

Push Notification Sender

What it Push Notification Sender?

- - - -

Push Notification Sender is a plugin that help you to send Push notification from any website using SiberianCMS API.

Quickstart

- - - -

To start using you will need 2 main things:

- 1- Upload Push Notification Sender on your server or your client server.
- 2- Create Siberian CMS API keys

How to upload files?


- - - -

To upload Push Notification Sender on your server you will need to use a FTP application like Filezilla or you can use your server control panel to upload the files.


How to create API keys in Siberian CMS?

To create API keys, First, you will need to log in to your back office.

Then go to Manage > Users > API



Click on • icon and enter the details, Make sure you grant access for Push notifications when you select the options.



Once you add the user, Save the details and go to next.

How configure Push Notification Sender?

```
config.php

1  <?php
2  session_start();
3

4  # Required Lib
5  require 'lib/Api.php';
6  require 'lib/Response.php';
7  require 'lib/Response.php';
9  # Basic Siberian Auth
14  $domain = ""; // Your platform URL
15  $username = ""; // Your API username
16  $spassword = ""; // Your API password
17  \Siberian\Api::init($domain, $username, $password);
18  # Bearer Siberian Auth
19  $bearerToken = ""; // Your api bearer token
19  \Siberian\Api::init\WithBearer($domain, $bearerToken);
11  */
22  # Admin ID
24  $admin_id = 0; // 0 = ALL
25  # Protect page with password
26  $page_locked = false; // true or false
27  $page_locked = false; // true or false
28  $page_password = "";
29  7>
```

- 1- Open Config.php file with your favourite editor.
- 2- To use Basic authorization, Enter the API keys details in lines 11,12,13.
- 3- To use Bearer authorization, delete line 17+21, Enter the API keys details in lines 18,19.
- 4- Enter Admin ID if you want to show apps for specific user, Or o to show all apps.
- 5- You are done!

How to protect page with password?

```
config.php

config.php

session_start();

# Required Lib

require 'lib/Api.php';
require 'lib/Response.php';
require 'lib/Response.php';

# Basic Siberian Auth

sdomain = ""; // Your platform URL

susername = ""; // Your API username

spassword = ""; // Your API password

\Siberian\Api::init($domain, $username, $password);

# Bearer Siberian Auth

/*

# $domain = ""; // Your platform URL

sbearerToken = ""; // Your platform URL

sbearerToken = ""; // Your api bearer token

\Siberian\Api::init\therefore bearer($domain, $bearerToken);

*/

# Admin ID

sadmin_id = 0; // 0 = ALL

# Protect page with password

spage_locked = false; // true or false

spage_password = "";

?>
```

- 1- Open Config.php file with your favourite editor.
- 2- Edit line 27, Change false to true.
- 3- Enter your password in line 28.

Support

- - - -



Client area: https://my.weappz.com

Don't hesitate to contact us anytime if you need any help!